
Ansible Tower Quick Setup Guide

Release Ansible Tower 3.0.2

Red Hat, Inc.

Jun 06, 2017

CONTENTS

1 Quick Start	2
2 Login as a Superuser	3
3 Import a License	5
4 Examine the Tower Dashboard	7
5 The Settings Menu	9
6 Review the Organization	10
7 Add a User to the Organization	12
8 Create a new Inventory and add it to the Organization	14
9 Create a Credential	16
10 Setting up a Project	18
11 Create a new Job Template	20
12 Launch it!	22
13 Index	25
14 Copyright © 2016 Red Hat, Inc.	26
Index	27

Thank you for your interest in Ansible Tower by Red Hat. Ansible Tower is a commercial offering that helps teams manage complex multi-tier deployments by adding control, knowledge, and delegation to Ansible-powered environments.

The *Ansible Tower Quick Setup Guide* covers basic steps for using Ansible Tower and running your first playbook. This document has been updated to include information for the latest release of Ansible Tower 3.0.2.

Ansible Tower Version 3.0.2; Aug 31, 2016; <https://access.redhat.com/>

QUICK START

Welcome to the Ansible Tower Quick Start Guide. At the end of the Quick Start, you will have a functioning Tower application that you can use to launch more sophisticated playbooks. You can expect the Quick Start process to take less than thirty minutes.

To begin, you must install Tower and you must choose a target system where an initial playbook can be deployed (provided by (Ansible Tower)). This first playbook executes simple Ansible tasks, while teaching you how to use Tower, as well as ensuring its proper setup. This can be any sort of system manageable by Ansible, as described at: http://docs.ansible.com/intro_installation.html.

Note: Ansible Tower is available in several license types: Self-Support, Enterprise: Standard, and Enterprise: Premium. These licenses vary in price, support-levels, and features. Enterprise: Standard and Enterprise: Premium license users will have access to some extended Tower features that Self-Support users will not have available. For more information about licenses and features, refer to [Licensing, Updates, and Support](#) in the Tower Installation and Reference Guide.

This Quick Start Guide covers setting up with a Self-Support level license in mind. Features only available to Enterprise: Standard or Enterprise: Premium license users are noted as you go along.


LOGIN AS A SUPERUSER

Using the login information provided after your installation completed, open a web browser and log in to Tower by browsing to the Tower server URL at: `https://<Tower server name>/`

Refer to [The Setup Playbook](#) in the *Tower Installation and Reference Guide* for more information.

Note: Tower installs a self-signed certificate for HTTPS communication which may require acceptance in your browser. Refer to the [General Installation Notes](#) in the *Tower Installation and Reference Guide* for help with replacing this certificate if needed.

Log in using the username and password set during the installation process. By default, this is username: *admin* and password: *password*.

These defaults can be changed later by clicking on the Settings () Menu button and selecting the Users navigational link.



Welcome to Ansible Tower! Please sign in.

USERNAME

admin

PASSWORD



.....

SIGN IN

IMPORT A LICENSE

Tower requires a valid license to run. If you did not receive a license from Ansible directly or via email, or have issues with the license you received, refer to <http://www.ansible.com/license> for free and paid license options (including free trial licenses) or contact Ansible via the Red Hat Customer portal at <https://access.redhat.com/>.

To add your license, you must browse to the location where you saved your license (or save the license contents to a text file locally, if needed) and upload it. The uploaded license may be a plain text file or a JSON file, and must include properly formatted JSON code. Once uploaded, agree to the End User License Agreement and click **Submit**.



TOWER LICENSE

Welcome to Ansible Tower! Please complete the steps below to acquire a license.

1

Please click the button below to visit Ansible's website to get a Tower license key.

REQUEST LICENSE

2

Choose your license file, agree to the End User License Agreement, and click submit.

* LICENSE FILE

BROWSE

No file selected.

* END USER LICENSE AGREEMENT

TOWER SOFTWARE END USER LICENSE AGREEMENT

Unless otherwise agreed to, and executed in a definitive agreement, between Ansible, Inc. ("Ansible") and the individual or entity ("Customer") signing or electronically accepting these terms of use for the Tower Software ("EULA"), all Tower Software, including any and all versions released or made available by Ansible, shall be subject to the Ansible Software Subscription and Services Agreement found at www.ansible.com/subscription-agreement ("Agreement"). Ansible is not responsible for any additional obligations, conditions or warranties agreed to between Customer and an authorized

☐ I agree to the End User License Agreement

SUBMIT

Copyright © 2016 Red Hat, Inc.

Once your license has been accepted, Tower navigates you to the main Ansible interface for the Dashboard (which you can access by clicking on the Ansible Tower logo at the top left of the screen as well).

For later reference, you can view this license from the Settings () Menu's 'VIEW YOUR LICENSE' link.

DETAILS

LICENSE	Valid License
VERSION	3.0.0
LICENSE TYPE	Enterprise
SUBSCRIPTION	Enterprise Tower Up To 10000 Nodes
LICENSE KEY	E6242476b1e52223d599936fd50994e642618ad77478186f558e80234ac19f0a
EXPIRES ON	07/19/2016
TIME REMAINING	34 Days
HOSTS AVAILABLE	10000
HOSTS USED	1
HOSTS REMAINING	9999

If you are ready to upgrade, please contact us by clicking the button below

UPGRADE

LICENSE MANAGEMENT

Choose your license file, agree to the End User License Agreement, and click submit.

* LICENSE FILE

BROWSE No file selected.

* END USER LICENSE AGREEMENT


TOWER SOFTWARE END USER LICENSE AGREEMENT

Unless otherwise agreed to, and executed in a definitive agreement, between Ansible, Inc. ("Ansible") and the Individual or entity ("Customer") signing or electronically accepting these terms of use for the Tower Software ("EULA"), all Tower Software, including any and all versions released or made available by Ansible, shall be subject to the Ansible Software Subscription and Services Agreement found at www.ansible.com/subscription-agreement ("Agreement"). Ansible is not responsible for any additional obligations, conditions or warranties agreed to between Customer and an authorized distributor, or reseller, of the

☐ I agree to the End User License Agreement

SUBMIT


EXAMINE THE TOWER DASHBOARD

Note: Ansible Tower 3.0 provides a streamlined interface, with the Settings () button offering access to administrative configuration needs. Users of older versions of Ansible Tower (2.4.5 or older) can access most of these through the top-level navigational menu or from their “Setup” menu button.

The Tower Dashboard offers a friendly graphical framework for your IT orchestration needs. Across the top-left side of the Tower Dashboard, administrators can quickly navigate to their **Projects**, **Inventories**, **Job Templates**, and **Jobs**.


Across the top-right side of this interface, administrators can access the tools they need to configure organizations, users, groups, and permissions.


On the main Tower Dashboard screen, a summary appears listing your current **Job Status**. Also available for review are summaries of **Recently Used Job Templates** and **Recently Run Jobs**.



Note: Keep in mind that the goal of this Quick Start is to launch a simple playbook. To do this, a number of configuration options must be setup. Completing the quick start configuration tasks now ensures that Tower is configured properly and allows for easier executions of more involved playbooks later on.


THE SETTINGS MENU

To enter the Settings Menu screen for Ansible Tower, click the  button. This screen allows you to create your organizations, add credentials, add users and teams, schedule management jobs, and more. You can also view your license from the Settings Menu's 'View Your License' link.




REVIEW THE ORGANIZATION

An organization is a logical collection of users, teams, projects, and inventories. It is the highest level object in the Tower object hierarchy.

From the Settings () Menu screen, click on **Organizations**.

Note: Ansible Tower creates a default organization automatically. Users of Tower with a Self-support level license only have the default organization available and should **not** delete it. Users of older versions of Tower (prior to 2.2) will not see this default organization.



A default organization has been automatically created and is available to all users of Ansible Tower. It can be used as is or edited later as needed.

For the purpose of this Quick Start Guide, leave the default organization as is and click **Save**.

Note: If you are using Ansible Tower with a Basic license, you must use the default organization. Only Enterprise or Premium Tower licenses have the ability to add new organizations beyond the default.

TOWER

PROJECTS

INVENTORIES

JOB TEMPLATES

JOBS

admin

SETTINGS / ORGANIZATIONS / DEFAULT

DEFAULT

DETAILS

PERMISSIONS

NOTIFICATIONS

* NAME

Default

DESCRIPTION

CANCEL

SAVE

ORGANIZATIONS 1

+ ADD

NAME

SEARCH

DEFAULT

Place organization description here

0 USERS

0 TEAMS

1 INVENTORIES

1 PROJECTS

1 JOB TEMPLATES


0 ADMINS


ITEMS 1-1 OF 1

Copyright © 2016 Red Hat, Inc.

To edit the default organization later, expand its ‘Properties’ and enter the appropriate details, then save your changes. Enterprise and Premium Tower license users who want to add a new organization should refer to the [Organizations](#) section in the Tower User Guide.

ADD A USER TO THE ORGANIZATION

Expand the **Users** section at the bottom of the default organization you just saved (not from the Setting [] menu's User menu item).



DEFAULT | USERS 0

+ ADD USER

PLEASE ADD ITEMS TO THIS LIST

ORGANIZATIONS 1

+ ADD

NAME SEARCH

DEFAULT

Place organization description here

0 USERS 0 TEAMS

1 INVENTORIES 1 PROJECTS


1 JOB TEMPLATES 0 ADMINS

ITEMS 1-1 OF 1


Copyright © 2016 Red Hat, Inc.

To add a user, click the  button.

Since other users have not yet been created, the “admin” user is the only user listed. Select the checkbox beside the “admin” user to select it for this organization, then click **Save**.




After saving, the organization's user information becomes available for viewing and the new user you created appears on the list.



CREATE A NEW INVENTORY AND ADD IT TO THE ORGANIZATION

An inventory is a collection of hosts managed by Tower. Inventories are assigned to organizations, while permissions to launch playbooks against inventories are controlled at the user and/or team level. For more information, refer to [Inventories](#), [Users - Permissions](#), and [Teams - Permissions](#) in the “Tower User Guide”.


To review existing inventories, navigate to the **Inventories** main link. To create a new inventory, click the



Ansible Tower provides a demo inventory for you to use as you learn how Tower works. Click on the “Demo Inventory” link for the stock inventory provided by Ansible Tower.

Note that inventories are divided into groups and hosts. A group might represent a particular environment (e.g. “Datacenter 1” or “Stage Testing”), a server type (e.g. “Application Servers” or “DB Servers”), or any other representation of your environment.

The left side of the screen displays the groups that belong to the Demo inventory. The right side displays hosts.



Note: Prior to Ansible Tower 2.2, hosts could not be added to the Web Servers inventory before adding a group. If you are using an older version of Tower, click the “Plus” button above the ‘Groups’ section to add a group before adding a host.

For this example, suppose that the organization you created earlier has a group of web server hosts supporting the corporate CMS application. To add these hosts to the Web Servers inventory, create a “CMS Web” group. Click the **Save** button to create the group.

For the purposes of this Quick Start and to test that Tower is setup properly, a local host has been added for your use.

[INVENTORIES](#) / [DEMO INVENTORY](#) / [LOCALHOST](#)

LOCALHOST **ON**

*HOST NAME ? DESCRIPTION

localhost

VARIABLES ? ☒ YAML ☐ JSON


```
1 ansible_connection: local
```

CANCEL SAVE


Click **Cancel** (if no changes were made) or use the breadcrumb navigational links at the top of the Ansible Tower browser to return to the Inventories overview screen. Clicking **Save** does not exit the edit dialog.

CREATE A CREDENTIAL

Credentials authenticate the Tower user to launch Ansible playbooks, which can include passwords and SSH keys, against inventory hosts. You can also require the Tower user to enter a password or key phrase when a playbook launches using the credentials feature of Tower.



Create a new credential by browsing to and clicking on the **Credentials** link from the Settings () button.

Note: When setting up additional credentials, keep in mind that the user you assign must have root access or be able to use SSH to connect to the host machine.

SETTINGS / CREDENTIALS 

CREDENTIALS 1 + ADD

NAME ▼ SEARCH 🔍

NAME ▲	DESCRIPTION ⬆	TYPE	OWNERS	ACTIONS
Demo Credential		Machine	admin	 

ITEMS 1-1 OF 1

For the purpose of this Quick Start, a demo credential has been provided for your use.

Click on the “Demo Credential” link name or the Edit () button to review or edit this credential.



DEMO CREDENTIAL

DETAILS

PERMISSIONS

* NAME

Demo Credential

DESCRIPTION

ORGANIZATION ?

Q

* TYPE ?

Machine

TYPE DETAILS

USERNAME

admin

PASSWORD

SHOW

☐ Ask at runtime?

PRIVATE KEY PASSPHRASE

SHOW

☐ Ask at runtime?

PRIVILEGE ESCALATION ?

Choose a privilege escalation

VAULT PASSWORD

SHOW

☐ Ask at runtime?

PRIVATE KEY ?

CANCEL

SAVE


SETTING UP A PROJECT

A Project is a logical collection of Ansible playbooks, represented in Tower.


You can manage playbooks and playbook directories by either placing them manually under the Project Base Path on your Tower server, or by placing your playbooks into a source code management (SCM) system supported by Tower, including Git, Subversion, and Mercurial.

Note: It is recommended that, whenever possible, you use source control to manage your playbooks. This type of best practice provides the ability to treat your infrastructure as code and is in line with DevOps ideals. While this Quick Start Guide uses lightweight examples to get you up and running, we suggest using source control to manage playbook for production purposes.

To review existing projects or to create a new one, navigate to the **Projects** main link.



Ansible Tower simplifies the getting started process by providing you with a Demo Project to work with initially.

Click on the “Demo Project” name link or click on the Edit () button to review the stock project provided by Ansible Tower.

PROJECTS / DEMO PROJECT

DEMO PROJECT

DETAILS

PERMISSIONS

NOTIFICATIONS

* NAME

Demo Project

DESCRIPTION

* ORGANIZATION

Q

Default

* SCM TYPE

Git

SOURCE DETAILS

* SCM URL

https://github.com/ansible/ansible-tower-samples

SCM BRANCH

SCM CREDENTIAL

Q

SCM UPDATE OPTIONS

☐ Clean

☐ Delete on Update

☒ Update on Launch

CACHE TIMEOUT (SECONDS)

0


^

v

CANCEL

SAVE

Click **Cancel** (if no changes were made) or use the breadcrumb navigational links at the top of the Ansible Tower browser to return to the Inventories overview screen. Clicking **Save** does not exit the edit dialog.

Before this project can be used in a job template, you must manually start an inventory sync for this project. Update the SCM-based demo project by clicking the  button under the project's available Actions.

Note: Please note that immediately after adding new projects setup to use source control, a “sync” automatically starts that fetches the project details from the configured source control. Because the “Demo” project is pre-stocked, however, you must manually start the inventory sync in order for this project to be used in a job template.

Notice that the status dot beside the name of the project updates once the sync has run.






PROJECTS

PROJECTS 1

+ ADD

STATUS


FILTER

NAME	TYPE	LAST UPDATED	ACTIONS
 Demo Project	Git	7/11/2016 11:48:46 AM	   


ITEMS 1-1 OF 1

CREATE A NEW JOB TEMPLATE

A job template combines an Ansible playbook from a project and the settings required to launch it. Review existing jobs or create a new job template by browsing to **Job Templates**.



For the purpose of this Quick Start, a Demo Job Template has been created for your initial use.

Click on the “Demo Job Template” name link or click on the Edit () button to review the stock job template provided by Ansible Tower.

TOWER

PROJECTS

INVENTORIES

JOB TEMPLATES

JOBS

admin

JOB TEMPLATES / DEMO JOB TEMPLATE

DEMO JOB TEMPLATE

DETAILS

COMPLETED JOBS

PERMISSIONS

NOTIFICATIONS

* NAME

Demo Job Template

DESCRIPTION

* JOB TYPE

Run

☐ Prompt on launch

* INVENTORY

Q

Demo Inventory

☐ Prompt on launch

* PROJECT

Q

Demo Project

* PLAYBOOK

hello_world.yml

* MACHINE CREDENTIAL

Q

Demo Credential

☐ Prompt on launch

CLOUD CREDENTIAL

Q

NETWORK CREDENTIAL

Q

FORKS

0

LIMIT

☐ Prompt on launch

* VERBOSITY

0 (Normal)

JOB TAGS

☐ Prompt on launch

OPTIONS

☐ Enable Privilege Escalation

☐ Allow Provisioning Callbacks

LABELS

EXTRA VARIABLES

YAML JSON

1

☐ Prompt on launch

ADD SURVEY

CANCEL

SAVE

JOB TEMPLATES 1

+ ADD

NAME

SEARCH

Q


NAME	DESCRIPTION	ACTIVITY	LABELS	ACTIONS
Demo Job Template				<div></div> <div></div> <div></div> <div></div> <div></div>


ITEMS 1-1 OF 1

Click **Cancel** (if no changes were made) or use the breadcrumb navigational links at the top of the Ansible Tower browser to return to the Inventories overview screen. Clicking **Save** does not exit the edit dialog.


CHAPTER TWELVE

LAUNCH IT!

From the Job Templates overview screen, click the Launch () button (under Actions) to run this Job Template.



The initial job launch returns a status page which updates automatically using Tower's Live Event feature until the job is complete.



Once complete, the job results look like the following:

RESULTS

STATUS	Successful	TEMPLATE	Demo Job Template
STARTED	7/11/2016 12:41:04 PM	JOB TYPE	Run
FINISHED	7/11/2016 12:41:11 PM	LAUNCHED BY	admin
ELAPSED	00:00:07	INVENTORY	Demo Inventory
PROJECT	Demo Project	PLAYBOOK	hello_world.yml
MACHINE CREDENTIAL	Demo Credential	VERBOSITY	Default

EXTRA VARIABLES

1	
---	--

STANDARD OUT

```
PLAY [Hello World Sample] *****
TASK [setup] *****
ok: [localhost]
TASK [Hello Message] *****
ok: [localhost] => {
  "msg": "Hello World!"
}
PLAY RECAP *****
localhost : ok=2  changed=0  unreachable=0  failed=0
```

DETAILS

1 Please select from a play below to view its associated tasks.

PLAY NAME	Q	ALL	FAILED
PLAYS	STARTED	ELAPSED	
Hello World Sample	12:41:09	00:00:02	

2 Please select a task below to view its associated hosts

TASK NAME	Q	ALL	FAILED
TASKS	STARTED	ELAPSED	HOST STATUS
setup	12:41:09	00:00:01	1
Hello Message	12:41:11	00:00:00	1

3 Please select a host below to view associated task details.

HOST NAME	Q	ALL	FAILED
HOSTS	ITEM	MESSAGE	
localhost			

EVENT SUMMARY

4 Please select a host below to view a summary of all associated tasks.

HOST NAME	Q	ALL	FAILED
HOSTS	COMPLETED TASKS		
localhost	2		

HOST STATUS SUMMARY

OK: 100%

For more details on the job results, refer to [Jobs](#).

Congratulations! Your Tower installation is officially setup and running properly. To learn more about these Tower features or to learn about administration tasks, the Tower API, etc., refer to the following documentation sets:

- [Ansible Tower User Guide](#)
- [Ansible Tower Installation and Reference Guide](#)
- [Ansible Tower Administration Guide](#)
- [Ansible Tower API Guide](#)
- [Ansible Tower Release Notes](#)
- [Ansible Documentation](#).

INDEX

- `genindex`

COPYRIGHT © 2016 RED HAT, INC.

Ansible, Ansible Tower, Red Hat, and Red Hat Enterprise Linux are trademarks of Red Hat, Inc., registered in the United States and other countries.

If you distribute this document, or a modified version of it, you must provide attribution to Red Hat, Inc. and provide a link to the original version.

Third Party Rights

Ubuntu and Canonical are registered trademarks of Canonical Ltd.

The CentOS Project is copyright protected. The CentOS Marks are trademarks of Red Hat, Inc. (“Red Hat”).

Microsoft, Windows, Windows Azure, and Internet Explore are trademarks of Microsoft, Inc.

VMware is a registered trademark or trademark of VMware, Inc.

Rackspace trademarks, service marks, logos and domain names are either common-law trademarks/service marks or registered trademarks/service marks of Rackspace US, Inc., or its subsidiaries, and are protected by trademark and other laws in the United States and other countries.

Amazon Web Services”, “AWS”, “Amazon EC2”, and “EC2”, are trademarks of Amazon Web Services, Inc. or its affiliates.

OpenStack™ and OpenStack logo are trademarks of OpenStack, LLC.

Chrome™ and Google Compute Engine™ service registered trademarks of Google Inc.

Safari® is a registered trademark of Apple, Inc.

Firefox® is a registered trademark of the Mozilla Foundation.

All other trademarks are the property of their respective owners.

INDEX

A

about Tower
 settings menu, 9

C

credentials
 create, 16
 settings menu, 9

D

dashboard, Tower
 examine, 7

I

inventory
 add to organization, 14
 create new, 14
inventory scripts
 settings menu, 9

J

job templates
 creation, 20
 launch, 22

L

launch
 job templates, 22
license
 import, 5
license, viewing, 9
log in
 Tower, 3

M

management jobs
 settings menu, 9

O

organization
 default, 10

 settings menu, 9

organizations, 10

P

projects, 18

Q

quick start, intro, 2

S

settings menu
 about Tower, 9
 credentials, 9
 inventory scripts, 9
 management jobs, 9
 organization, 9
 teams, 9
 users, 9
 view license, 9

T

teams
 settings menu, 9
Tower
 log in, 3
Tower settings menu, 9

U

users
 add new, 12
 add to organization, 12
 settings menu, 9

V

view license
 settings menu, 9